Program Optimization

CSci 2021: Machine Architecture and Organization April 6th-15th. 2020

Your instructor: Stephen McCamant

Based on slides originally by:

Randy Bryant, Dave O'Hallaron

Bryant and O'Hallaron, Computer Systems: A Programmer's Perspective Third Edition

Today

- Overview
- Generally Useful Optimizations
 - Code motion/precomputation
 - Strength reduction
 - Sharing of common subexpressions
 - Removing unnecessary procedure calls
- Optimization Blockers
 - Procedure calls
 - Memory aliasing
- Exploiting Instruction-Level Parallelism
- Dealing with Conditionals

Bryant and O'Hallaron, Computer Systems: A Programmer's Perspective, Third Edition

Performance Realities

There's more to performance than asymptotic complexity

- Constant factors matter too!
 - Easily see 10:1 performance range depending on how code is written
 - Must optimize at multiple levels:
 - algorithm, data representations, procedures, and loops
- Must understand system to optimize performance
 - How programs are compiled and executed
 - How modern processors + memory systems operate
 - How to measure program performance and identify bottlenecks
 - How to improve performance without destroying code modularity and generality

Bryant and O'Hallaron, Computer Systems: A Programmer's Perspective, Third Edition

Optimizing Compilers

- Provide efficient mapping of program to machine
 - register allocation
 - code selection and ordering (scheduling)
 - dead code elimination
 - eliminating minor inefficiencies
- Don't (usually) improve asymptotic efficiency
 - up to programmer to select best overall algorithm
 - big-O savings are (often) more important than constant factors
 - but constant factors also matter
- Have difficulty overcoming "optimization blockers"
 - potential memory aliasing
 - potential procedure side-effects

Bryant and O'Hallaron, Computer Systems: A Programmer's Perspective, Third Edition

Limitations of Optimizing Compilers

- Operate under fundamental constraint
 - Must not cause any change in program behavior
 - Except, possibly when program making use of nonstandard language features
 - Often prevents it from making optimizations that would only affect behavior under pathological conditions.
- Behavior that may be obvious to the programmer can be obfuscated by languages and coding styles
 - e.g., Data ranges may be more limited than variable types suggest
- Most analysis is performed only within procedures
 - Whole-program analysis is too expensive in most cases
 - Newer versions of GCC do interprocedural analysis within individual files
 - But, not between code in different files
- Most analysis is based only on static information
 Compiler has difficulty anticipating run-time inputs
- When in doubt, the compiler must be conservative

Bryant and O'Hallaron, Computer Systems: A Programmer's Perspective, Third Edition


Generally Useful Optimizations


- Optimizations that you or the compiler should do regardless of processor / compiler
- Code Motion
 - Reduce frequency with which computation performed
 - If it will always produce same result
 - Especially moving code out of loop

```
void set_row(double *a, double *b,
    long i, long n)
{
    long j;
    for (j = 0; j < n; j++)
        a[n*i+j] = b[j];
}
</pre>

    long j;
    int ni = n*i;
    for (j = 0; j < n; j++)
        a[ni+j] = b[j];
</pre>
```

Bryant and O'Hallaron, Computer Systems: A Programmer's Perspective, Third Edition





```
Share Common Subexpressions

Reuse portions of expressions

GCC will do this with -O1

| * Sum neighbors of i,j */ up = val(i(i-1)*n + j ); down = val(i(i-1)*n + j ); left t val(i*n + j-1); zight = val(i*n + j-1); zight = val(i*n + j-1); sum = up + down + left + right;

| * Smultiplications: i*n, (i-1)*n, (i+1)*n

| * leaq 1(%rsi), %rax # i*1 | imulq %rox, %rax # i*n+1 | imulq %rox, %rax # i*n+1 | imulq %rox, %rax # i*(i-1)*n | imulq %rox, %rax # i*n+j | imul
```

```
Optimization Blocker #1: Procedure Calls

Procedure to Convert String to Lower Case

\[
\begin{align*}
\size_t i; \\
\for \left(i = 0; i < \text{strlen(s); i++)} \\
\if (s[i] >= 'A' & \left s[i] <= 'Z') \\
\size_t [i] -= ('A' - 'a');
\]

Extracted from CMU 213 lab submissions, Fall, 1998

Similar pattern seen in UMN 2018 HA1
```

```
Convert Loop To Goto Form

void lower(char *s)
{
    size_t i = 0;
    if (i >= strlen(s))
        goto done;
    loop:
        if (s[i] >= 'A' && s[i] <= 'Z')
            s[i] -= ('A' - 'a');
        i++;
        if (i < strlen(s))
            goto loop;
        done:
    }

* strlen executed every iteration</pre>
```

Calling Strlen

```
/* My version of strlen */
size_t strlen(const char *s)
{
    size_t length = 0;
    while (*s != '\0') {
        s++;
        length++;
    }
    return length;
}
```

- Strlen performance
 - Only way to determine length of string is to scan its entire length, looking for null character.
- Overall performance, string of length N
 - N calls to strlen
 - Require times N, N-1, N-2, ..., 1
 - Overall O(N²) performance

Bryant and O'Hallaron, Computer Systems: A Programmer's Perspective, Third Edition

Improving Performance


```
void lower(char *s)
{
    size_t i;
    size_t len = strlen(s);
    for (i = 0; i < len; i++)
        if (s[i] >= 'A' && s[i] <= 'Z')
        s[i] -= ('A' - 'a');
}</pre>
```

- Move call to strlen outside of loop
- Since result does not change from one iteration to another
- Form of code motion

Bryant and O'Hallaron, Computer Systems: A Programmer's Perspective. Third Edition

Lower Case Conversion Performance

- Time doubles when double string length
- Linear performance of lower2



Optimization Blocker: Procedure Calls

- Why couldn't compiler move strlen out of inner loop?
 - Procedure may have side effects
 - Alters global state each time called
 - Function may not return same value for given arguments
 - Depends on other parts of global state
 - Procedure lower could interact with strlen
- Warning:
 - Compiler treats procedure call as a black box
- Weak optimizations near them
- Remedies:
 - Use of inline functions
 - GCC does this with -O1
 - Within single file
 But doesn't help here
- Do your own code motion

size_t lencnt = 0;
size_t strlen(const char *s)
{
 size_t length = 0;
 while (*s != '\0') {
 s++; length++;
 }
 lencnt += length;
 return length;
}

What About Larger Programs?

- If your program has just one loop, it's obvious where to change to make it go faster
- In more complex programs, what to optimize is a key question
- When you first write a non-trivial program, it often has a single major algorithm performance problem
 - Textbook's example: insertion sort
 - A program I wrote recently: missed opportunity for dynamic programming
 - Fixing this problem is way more important than any other changes

Amdahl's Law

- If you speed up one part of a system, the total benefit is limited by how much time that part took to start with
- Speedup S is:

$$S = \frac{1}{(1-\alpha) + \alpha/k}$$

where the acceleration factor is k and the original time fraction is α .

 Limiting case: even if k is effectively infinite, the upper limit on speedup is

$$S_{\infty} = \frac{1}{(1-\alpha)}$$

3

Knowing What's Slow: Profiling

- Profiling makes a version of a program that records how long it spends on different tasks
 - Use to find bottlenecks, at least in typical operation
- Common Linux tools:
 - gprof: GCC flag plus a tool to interpret output of the profiled program
 - Counts functions and randomly samples for time
 - Discussed in textbook's 5.14.1
 - Valgrind callgrind/cachegrind
 - Counts everything, precise but slow
 - OProfile
 - Uses hardware performance counters, can be whole-system

Exercise Break: Weird Pointers

Can the following function ever return 12, and if so how?

```
int f(int *p1, int *p2, int *p3) {
    *p1 = 100;
    *p2 = 10;
    *p3 = 1;
    return *p1 + *p2 + *p3;
}
```

Yes, for instance:

```
int a, b;
f(&a, &b, &a);
```

```
# Code updates b[i] on every iteration

**Code updates b[i] on every iteration

**Why couldn't compiler optimize this away?
```

```
Removing Aliasing

/* Sum rows of n X n matrix a and store in vector b */
void sum_rows2(double *a, double *b, long n) {
  long i, j;
  for (i = 0; i < n; i++) {
    double val = 0;
    for (j = 0; j < n; j++) {
        val + a(i*n + j);
        b(i) = val;
    }

# sum_rows2 inner loop
..llo:

adddd (%rdi), %xmm0 # FP load + add addq & %, *rdi
    cmpq %rax, %rdi
    jne ..llo

# No need to store intermediate results
```

```
Poptimization Blocker: Memory Aliasing

Aliasing

Two different memory references specify single location
Easy to have happen in C
Since allowed to do address arithmetic
Direct access to storage structures
Get in habit of introducing local variables
Accumulating within loops
Your way of telling compiler aliasing is impossible
```

Exploiting Instruction-Level Parallelism

- Need general understanding of modern processor design
 - Hardware can execute multiple instructions in parallel
- Performance limited by data dependencies
- Simple transformations can yield dramatic performance improvement
 - Compilers often cannot make these transformations
 - Lack of associativity and distributivity in floating-point arithmetic

```
Benchmark Example: Data Type for
Vectors
 /* data structure for vectors */
typedef struct{
                                            len
                                                               0 1 len-1
     size_t len;
data_t *data;
                                           data
   vec;
                                           /* retrieve vector element
                                           and store at val */
int get_vec_element
(*vec v, size_t idx, data_t *val)
  ■Data Types


    Use different declarations

                                                if (idx >= v->len)
    return 0;
*val = v->data[idx];
return 1;
         for data_t
      • int
       • long

    float

       • double
```

Benchmark Computation void combine1(vec_ptr v, data_t *dest) Compute sum or product of vector *dest = IDENT; for (i = 0; i < vec length(v); i++) { elements data_t val; get_vec_element(v, i, &val); *dest = *dest OP val; ■Data Types Operations Use different declarations Use different definitions of for data_t OP and IDENT • int + / 0 • long * / 1 float • double



```
Benchmark Performance
  void combine1(vec_ptr v, data_t *dest)
                                                    Compute sum or
                                                    product of vector
       *dest = IDENT:
      for (i = 0; i < vec length(v); i++) {
                                                    elements
         get_vec_element(v, i, &val);
*dest = *dest OP val;
Method
                            Integer
                                                   Double FP
Operation
                           Add
                                                   Add
                                                               Mul
Combine1
                          22.68
                                      20.02
                                                  19.98
                                                              20.18
unoptimized
Combine1 -O1
                          10.12
                                      10.12
                                                              11.14
```


```
Basic Optimizations


[void combine4 (vec_ptr v, data_t *dest) {
    long i;
    long length = vec_length(v);
    data_t *d = get_vec_start(v);
    data_t t = IDENT;
    for (i = 0; i < length; i++)
        t = t oP d[i];
    *dest = t;
}

■ Move vec_length out of loop

■ Avoid bounds check on each cycle

■ Accumulate in temporary
```








Superscalar Processor Definition: A superscalar processor


- Definition: A superscalar processor can issue and execute multiple instructions in one cycle. The instructions are retrieved from a sequential instruction stream and are usually scheduled dynamically.
- Benefit: without programming effort, superscalar processor can take advantage of the instruction level parallelism that most programs have
- Most modern CPUs are superscalar.
- Intel: since Pentium (1993)

Bryant and O'Hallaron, Computer Systems: A Programmer's Perspective, Third Edition









```
Loop Unrolling (2x1)

void unroll2a_combine(vec_ptr v, data_t *dest)
{
    long length = vec_length(v);
    long limit = length-1;
    data_t *d = get_vec_start(v);
    data_t x = IDENT;
    long i;
    /* Combine 2 elements at a time */
    for (i = 0; i < limit; i+=2) {
        x = (x OP d[i]) OP d[i+1];
    }
    /* Finish any remaining elements */
    for (; i < length; i++) {
        x = x OP d[i];
    }
    *dest = x;
}

■ Perform 2x more useful work per iteration</pre>
```

```
Effect of Loop Unrolling
         Method
                                             Double FP
         Operation
                            Add
                                     Mult
                                              Add
                                                       Mul
         Combine4
                            1.27
                                     3.01
                                              3.01
                                                       5.01
         Unroll 2x1
                            1.01
                                     3.01
                                              3.01
                                                       5.01
                                                       5.00
                            1.00
                                     3.00
                                              3.00
         Latency
         Bound


    Helps integer add


                                  x = (x OP d[i]) OP d[i+1];


    Achieves latency bound

■ Others don't improve. Why?


    Still sequential dependency
```











Loop Unrolling with Separate Accumulators (2x2) void unroll2a_combine(vec_ptr v, data_t *dest) { long length = vec_length(v); long limit = length-1; data_t *d = get_vec_start(v); data_t x 0 = IDENT; data_t x1 = IDENT; long i; /* Combine 2 elements at a time */ for (i = 0; i < limit; i+=2) { x0 = x0 OP d[i]; x1 = x1 OP d[i+1]; } /* Finish any remaining elements */ for (; i < length; i++) { x0 = x0 OP d[i]; } *dest = x0 OP x1; } Different form of reassociation Byant and Of Nallivon, Computer Systems. A Programmer's Perspective, Third Edition</pre>
















Achievable Performance Method Double FP Operation Best 0.54 1.01 1.01 0.52 Latency Bound 1.00 3.00 3.00 5.00 Throughput Bound 0.50 1.00 1.00 0.50 ■ Limited only by throughput of functional units Up to 42X improvement over original, unoptimized code





























Branch Prediction: Bad News

- Some program branches are inherently unpredictable
 - E.g., if based on input data, binary search tree, etc.
 - Indirect jumps are also often hard to predict
- These can be a major performance bottleneck
 - Misprediction penalty is typically 10-20 cycles
- Partial solution: write code to be compiled to conditional moves
 - For GCC: use math and ? : instead of if
 - Textbook gives min/max and mergesort examples

Bryant and O'Hallaron, Computer Systems: A Programmer's Perspective, Third Editio

Getting High Performance

- Good compiler and flags
- Don't do anything stupid
 - Watch out for hidden algorithmic inefficiencies
 - Write compiler-friendly code
 - Watch out for optimization blockers: procedure calls & memory references
 - Look carefully at innermost loops (where most work is done)
- Tune code for machine
 - Exploit instruction-level parallelism
 - Avoid unpredictable branches
 - Make code cache friendly (Covered later in course)

Bryant and O'Hallaron, Computer Systems: A Programmer's Perspective, Third Edition

11